

Lennart SCHWEERS

Premier objet

```
// Japanese-Style Knife in OpenSCAD
```

```
// Parameters for customization
```

```
blade_length = 150; // Length of the blade in mm
```

```
blade_width = 30; // Maximum width of the blade in mm
```

```
blade_thickness = 2; // Thickness of the blade in mm
```

```
handle_length = 100; // Length of the handle in mm
```

```
handle_width = 20; // Width of the handle in mm
```

```
handle_height = 15; // Height of the handle in mm
```

```
handle_offset = 3; // How much the handle extends into the blade
```

```
module knife() {
```

```
    translate([0, 0, 0]) blade();
```

```
    translate([-handle_offset, -handle_width / 2, -handle_height / 2]) handle();
```

```
}
```

```
// Blade Module
```

```
module blade() {
```

```
    difference() {
```

```
        // Blade Shape
```

```
        linear_extrude(height = blade_thickness) {
```

```
            polygon(points = [
```

```
                [0, 0],
```

```
                [blade_length, blade_width / 2],
```

```
                [blade_length, -blade_width / 2],
```

```
                [0, 0]
```

```
            ]);
```

```
        }
```

```
        // Bevel Edge (sharpness)
```

```
        translate([blade_length / 2, 0, 0]) {
```

```
            rotate([0, 0, 90]) {
```

```
                cylinder(r1 = blade_thickness, r2 = 0, h = blade_length, center = true);
```

```
            }
```

```
        }
```

```
    }
```

```
}
```

```
// Handle Module
module handle() {
    hull() {
        // Create a smooth transition from blade to handle
        translate([0, 0, 0]) cube([handle_offset, handle_width, handle_height]);
        translate([handle_length, 0, 0]) cube([handle_offset, handle_width, handle_height]);
    }
    difference() {
        // Main handle block
        translate([0, -handle_width / 2, -handle_height / 2])
        cube([handle_length, handle_width, handle_height], center = true);
    }
}

// Render the knife
knife();
```

Deuxième Objet: Vase

// Alvar Aalto-style vase approximation in OpenSCAD

\$fn = 100; // Increase for smoother curves

// Parameters

height = 200; // Height in mm (20 cm)

thickness = 3; // Wall thickness in mm

```
difference() {
    // Outer vase shape
    linear_extrude(height)
        offset(r=30) // Offset to round the corners
        union() {
            circle(30, $fn=100);
            translate([50, 0]) circle(25, $fn=100);
            translate([-50, 0]) circle(25, $fn=100);
            translate([0, 50]) circle(20, $fn=100);
        };
}
```

// Inner cavity (subtracting inner shape)

```
translate([0, 0, 0])
    linear_extrude(height - thickness)
        offset(r=25)
        union() {
            circle(27, $fn=100);
```

```
    translate([50, 0]) circle(22, $fn=100);  
    translate([-50, 0]) circle(22, $fn=100);  
    translate([0, 50]) circle(17, $fn=100);  
};  
}
```

Revision #5

Created 12 December 2024 15:40:05 by Schweers Lennart

Updated 12 December 2024 16:00:56 by Schweers Lennart